

Spektrum Smart Checker

Update instructions and Change Log

2019 – March – 6



Items Needed to Perform Update

- A Windows Operating System PC (Windows 7 and up)
- A Micro USB cable
- Spektrum Smart Battery Checker XBC100
- A Battery to power the checker via the iC3 port


Step by Step

1. Download the latest XBC100 updater [here](#)
2. Once downloaded, **extract** the .ZIP file to a location that you can easily find, we suggest the Desktop
3. Locate the SCU.exe file and open/execute
4. You will be presented with this screen ->
5. **Connect** your XBC100 Smart checker to your PC

- Plug in a battery into your Smart Checker
- Then plug in the Micro USB into the Smart Checker
- The lower portion of the screen will then display the Device and App version currently on your XBC100

- *IF the device does not connect, click the **Driver** button to install the appropriate driver*

6. Click the **Update** button to install the update on your XBC100. A progress bar will appear on your computer screen and the screen on your XBC100 will notify that an update is in progress.
7. Wait until the update is complete, and enjoy!



Change Log

XBC100 V1.0.0.8

1. Correction for voltage percentage calculation.

XBC100 V1.0.0.7

1. Add Italian language.
2. Add Operating instructions in the servo screen.

XBC100 V1.0.0.5

1. Improved UI display

XBC100 V1.0.0.4

1. Improved UI display

XBC100 V1.0.0.2

1. Init Version